

Audylic ‘SmartWatch’ Folder, V0.9.8.0 18 Oct 2024

Changelog since version 0.9.5 March 2024

0.9.5b July 2024 Account credit is displayed in bottom left corner of app window, app will not submit file with no credit available.

0.9.7 September 2 2024 - Option added to change API address in settings from <https://portal.audylic.com/api> (cloud version) to local address <http://localhost:5080/api> (stand-alone private version) or any other private IP address.


Version 0.9.7.1- Upgraded network code to improve the logout function. Added an icon for the macOS version. Configured credits to display only when the API URL is audylic.com. Introduced a "Resubmit Files with Errors" option in the Queue menu.

Version 0.9.7.2 Colour palette modified to Audylic colours, ratified version numbering convention.


Version 0.9.8.0 Added mp3 encoding for processed files, and support for stand-alone local hosting, support for instances with different configurations.

Instructions –


1. Download the ZIP file, (Windows version) save to somewhere on your PC where you can find it and extract the ‘SmartWatch’ Hot folder app for Windows from the downloads section of the Audylic website. If required, create a shortcut to the “AudylicDesktop.exe” file.
2. For the MacOS version, double click on the ‘Audylic.DMG’ file , drag the ‘Audylic.app’ to the applications folder. To run, open the Audylic app.
3. If you have a previous version of ‘Smartwatch, you can if required to tick the ‘reset’ option in ‘File> Settings’ and redefine your folders for watching and saving, and the preset or presets you require, if you do not, it will remember settings from previous installations, *You can run multiple instances of the app if you want to use different presets for different folders.* This is optional, however, and running a later version will read the previous version’s settings (See 13: - see cautions and maintenance at the end of this manual).
4. Optionally, If audio processing of video files is required, download, save and extract the FFmpeg Windows package from <https://www.ffmpeg.org/download.html>
5. Open the file ‘AudylicDesktop.exe’ after it opens, you should see the following window:





6. Click on 'File' > 'Setup'



8. Browse to the location where you extracted the FFMPEG files to, open the 'bin' folder and locate ffmpeg.exe, then select 'OK'.




7. Click on the 'Settings' button, (If already logged in, you will have to log out, close and reopen the application) and if required, change the API address URL, for the cloud version, the URL should be left at the default which is <https://portal.audyllic.com/api> For the local version on the same PC it should be <http://localhost:5080/api> or for another private address within the network, for example <http://192.168.3.22:5080/api> if the Audyllic stand alone version was installed on a PC or server with a local address of 192.168.3.22.




When finished setting the URL, Click on 'OK'.


8. Click on 'File' > 'Setup'




9. Set up the folders you want watched and to save processed files to




Click 'Next'.




There is an option to convert the finished file to MP3 as well as a WAV file, you can also set the MP3 bitrate as desired, deselect the tick box if an MP3 copy is not required.



Click 'Next', then select the output folder



10. Select the preset required – if you want to use different presets for different files, open another instance of the watch folder, and choose a different preset and optionally different input and / or output folders




Finished

The folder "E:/Audylic audio and video/Watchvid1 in" will be watched by the application.

Files detected will be submitted to Audylic using preset "2: Natural Radio Sound: Voice and Music -16LUFS"



The processed file from Audylic will be stored at "E:/Audylic audio and video/Watchvid1 out"

You will be able to modify these settings using the File-> Setup menu



You can open and set up multiple instances of the 'Watch' Folder app, each with different settings, watched and ooutput folders and presets if required

11. The Audyllic 'Smart Watch Hot folder app will now automatically upload any new files that appear in the monitored folder. You can also manually add a file using the 'Add file' button.



12. There is *no need* to log in to your Audyllic portal web account, but if you do, you will see your files progress. If you have notifications enabled in Windows, you will see a notification

To start a new job, choose a file and select "Upload Job":

File: No file selected.

Preset:

Your jobs

#	Date	Name	Duration	Status
1552	14. Mar 2024	audioFrom-IMG_1571.mp4.wav Natural Radio Sound: Voice and Music -16LUFS	6:43	Processing <div style="width: 50%; background-color: #007bff; height: 5px;"></div>

13. If the file is a video format file, as well as your video file with processed audio, you will also get a WAV file of both pre and post processed audio – useful for an audio only version of a video podcast for example!


> 500GB (E:) > Audyllic audio and video > Watchvid1 in

Name	#	Title	Contributing artists
audioFrom-IMG_1571.mp4.wav			
IMG_1571.mp4			

500GB (E:) > Audyllic audio and video > Watchvid1 out

Name	#	Title
audioFrom-IMG_1571-2_Natural Radio Sound_Voice and Music -16LUFS.mp4.wav		
IMG_1571 - 2_Natural Radio Sound_Voice and Music -16LUFS 155355.mp4		


If there is credit in your account, you will see the amount available in minutes in the bottom left corner of the app after processing. If there is no credit available, the Watch App will not submit files for processing to the Audyllic server. (This will not display, if logged into a locally hosted version of the Audyllic service as credit is not relevant)



Maintenance and settings - Proceed with caution!

The following are details of how to reset or uninstall the Watch folder program

14. If you want to reset all settings, go to 'File' > 'Settings', and tick the 'Reset settings' box. **Caution.** You will have to re-enter the watched folders, and any files still there may be resubmitted to the Audyllic server.



15. Restart the program, re- enter your log in details (if resetting, or updating or changing from cloud to local stand-alone version).
16. You can delete the 'settings.xml' file by going to the "Audyllic desktop" folder inside your Appdata/local folder. i.e. C:\Users\

17. To uninstall, just delete the Watch folder that you saved in step 1, and delete the 'settings.xml' file as in step 15.